Trnum - A Program To Number Figures

Matt Bishen

July, 1985

Research Institute for Advanced Computer Science
NASA Ames Research Center

RIACS TR 85.7

(NASA-CR-184899) TRNUM: A PROGRAM TO NUMBER FIGURES (Research Inst. for Advanced Computer Science) 26 p

N90-71368

Unclas 00/61 0295387



Research Institute for Advanced Computer Science

Trnum - A Program To Number Figures

Matt Bishop

Research Institute for Advanced Computer Science NASA Ames Research Center Moffett Field, CA 94035

ABSTRACT

Trnum is a preprocessor for NROFF and TROFF text which enables users to label figures, displays, tables, and equations symbolically. This program then translates the labels into consecutive integers which may be printed in a variety of formats. In addition, prefixes and suffixes may be defined in such a way that they are automatically prepended or appended to the number. A number of different counters may be used, and the symbols may appear anywhere in the body of the paper. This document contains a tutorial as well as a detailed description of the program.

July 17, 1985

Trnum - A Program To Number Figures

Matt Bishop

Research Institute for Advanced Computer Science NASA Ames Research Center Moffett Field, CA 94035

I. Introduction

A problem which authors of papers often have is that of numbering figures or equations while the paper is being written. One finds that a new picture, or equation, must be inserted between two others; as a result, the numbering of all such diagrams after the newly-inserted one is not correct. Tracking down the numbers, and correcting them, is very time-consuming and painstaking. More often than not, one will overlook a number; the result may be that the reader will become confused.

Trnum is intended to alleviate this problem. It enables the user to label something with a pair of names; when a new figure is inserted, the user need not change any of the pairs in the text. Trnum numbers pairs in the order in which they occur, thereby relieving the user of the burden of changing all the numbers of the figures after the one inserted.

This document has 6 sections. The second gives an overview of the program, the third describes the labels which trnum replaces with numbers, and the fourth lists miscellaneous commands. Invoking this program under UNIX† is

[†] UNIX is a Trademark of Bell Laboratories.

described in the fifth section. The last section is a tutorial on using trnum. An appendix tersely summarizes the information, for quick reference.

II. Overview

Trnum copies most text from its input files to the standard output; certain strings called pairs (which are described in the next section) are replaced by labels, and lines beginning with ".\" trnum:" allow the user to force certain actions to occur. These will be discussed separately.

Trnum maintains 101 counters, each of which begins at 1 and increases as new symbols are defined. The user may name these counters as he pleases. Each counter allows 2039 different symbols, the names of which the user chooses; a symbol may be defined in as many counters as the user likes. Each counter and symbol pair represents a different label; two different counters may have symbols with the same name, but the numbers associated with the two pairs need not be the same.

When a counter is created, certain attributes associated with that counter are set as indicated by that pair. These attributes are the prefix (a string which is printed before the number associated with the pair), the suffix (a string which is printed after the number associated with the pair), and the format (a character indicating how the number associated with the pair is to be printed). Whenever this counter is referenced, unless new values of these attributes are given in the pair referencing that counter, the values used will be those associated with the counter.

III. Pairs

A counter and symbol is referred to by a sequence of characters called a pair, which has the following format:

$$<[prefix+][counter.][symbol][:format][-suffix]>$$

The brackets enclose parts of the pair associated with one another. In detail, the parts are:

prefix This is a sequence of characters terminated by "+". It is prepended to the number associated with the counter and symbol.

The default is the null string.

counter This is a sequence of alphanumeric characters terminated by "."

(period). It names the counter to which the symbol refers. The default is the counter "default".

symbol This is a sequence of alphanumeric characters which names the symbol. There is no default.

This character indicates in what form the number associated with the counter and symbol is to be printed, and it is preceded by ":" (colon). The available formats are:

Format	Numbering Sequence	
1	0,1,2,3,4,5,	
001	000,001,002,003,004,005,	
i	0,i,ii,iii,iv,v,	
I	0,I,II,III,IV,V,	
a	0,a,b,c,,z,aa,ab,,zz,aaa,	
A	0,A,B,C,,Z,AA,AB,,ZZ,AAA,	

An Arabic format having n digits specifies a field width of n digits

(see the entry for 001 in the table.) Note the formats are the same as for the macro ".af" in NROFF and TROFF. The default format is format 1 (Arabic numbers in the form of line 1 of the above table.)

This is a sequence of characters preceded by "-" and terminated by ">". It is appended to the label number associated with the counter and symbol. The default suffix is the null string.

Notice that any character except "+", ".", ":", "-", "<", ">", ">", and "%" may appear in the prefix and the suffix; to put of these characters (called control characters) in the prefix or suffix, precede it with the quote character "%". (For example, "%" in the prefix will set the prefix to "%".) Only letters (both upper and lower case), digits, and the underscore character may appear in counter and symbol names. In addition, the format string must be one of the ones described there (that is, "i", "I", "a", "A", or a string of 1 or more Arabic digits); erroneous formats are not caught. If a sequence of characters does not meet the description above, trnum will assume the sequence is not a pair and simply copy it to the output. In general, this is trnum's approach to all input: if it is a pair, replace it — otherwise, copy it.

One of the symbol and counter names must be present; any of the other parts of the pair may be omitted. In all cases where a symbol name is present, the appropriate default associated with the counter is used when something is omitted. (If the counter name is omitted, the name "default" is used.) If the symbol name is omitted, but the counter name is present, the pair is copied to the output, but any counter referenced by it (the one named "default", if no

name is given explicitly) is created and initialized. This is most useful when the default attributes of the counter are to be set differently than the values required the first time the counter is used.

Here are some examples of pairs:

A counter is defined whenever it is first encountered, so if the counter "fig" has not been used before this pair occurs, this pair will define it, and set the default prefix, suffix, and format for that counter to the strings "Figure", ".", and "I", respectively. (Notice that the blank in the prefix need not be quoted.) In this case, the text "Figure I." would replace the pair. If the counter had been encountered before (for this example, suppose "fifo_queue" were the fourth symbol defined for that counter), regardless of the attributes associated with the counter "fig", the pair would be replaced by "Figure IV.", since any attributes named explicitly in the pair override the default attributes associated with the counter. Thus, to suppress the prefix and suffix and force Arabic format, give explicitly null attributes (for the above example,

will suppress all default attributes and use the default, Arabic, format.)

<maintheorem>

This defines a symbol, "maintheorem", which is associated with the default counter. It will be printed as an Arabic numeral. If the pair

<maintheorem:i>

is encountered later on, the number associated with the symbol "maintheorem" and counter "default" will be printed as a lower-case Roman numeral.

IV. Verbs

Occasionally it is useful to be able to exercise more detailed control over counters and their component symbols. For example, when beginning a new chapter of a thesis, certain counters, such as a subsection number counter, should be reset. *Trnum* offers these capabilities by means of *verbs*.

A verb is a command indicating that special action is to be taken. It is given on a line beginning with ".\" trnum:", immediately following the colon (blank spaces may be put between the colon and the verb.) Note these lines are treated as comment lines by NROFF and TROFF and so are ignored. Only enough of the verb to identify it uniquely need be given. Any arguments to the verb are placed after it. The verbs are:

change the character indicating that a pair begins to the first character of the first argument to the verb; for example,

.\" trnum: begin (

indicates that pairs will begin with "(". Initially, this character is "<".

control This macro prints on the error output (usually the terminal) the control characters and verbs.

This verb indicates the pairs named as arguments are to be defined.

It is useful when pairs must be numbered in an order other than that in which they occur. If the symbol name in a pair is omitted, the counter is initialized but no symbol is entered.

end

Change the character indicating that a pair ends to the first character of the first argument to the verb; for example,

.\" trnum: end)

indicates that pairs will end with ")". Initially, this character is ">".

format

Change the character indicating the format begins to the first character of the first argument to the verb; for example,

.\" trnum: format #

indicates that the format description will begin with "#". Initially, this character is ":" (colon).

off

This verb turns off the interpretation of pairs; trnum just copies the input to the output until interpretation is turned back on (see on, below.) It is useful when escaping character sequences which look like pairs but are not pairs, and which trnum would otherwise replace with numbers. (An alternative is to quote the beginning character of the pair.)

on

This verb turns on the interpretation of pairs. See off, above.

prefix

Change the character terminating the prefix of the first argument to the verb; for example,

.\" trnum: prefix;

indicates that prefixes will end with ";". Initially, this character is "+".

print

This macro prints to the error output (usually the terminal) the

label associated with any pairs given as arguments. If the symbol name is omitted, the labels of all symbols associated with the named counter are printed; if the counter name is omitted, the labels of all symbols with that name (in all counters) are printed; and if both the symbol and counter names are omitted, the labels of all defined pairs are printed.

quote

Change the quote character to the first character of the first argument to the verb; for example,

.\" trnum: quote \

indicates that the quote character will be "\". Initially, this character is "%".

reset

This macro indicates the pairs named as arguments are to be reset; it is identical to undefining the pair, then defining it again, and is included as a convenience.

separator

Change the character separating the counter name from the symbol name to the first character of the first argument to the verb; for example,

.\" trnum: separator,

indicates that the counter name and the symbol name will be separated by ",". Initially, this character is ".".

suffix

Change the character indicating the suffix begins to the first character of the first argument to the verb; for example,

.\" trnum: suffix *

indicates that suffixes will begin with "*". Initially, this character is "-".

terse

This turns off verbose mode.

undefine

This verb indicates the pairs named as arguments are to be undefined. It deletes them from the appropriate counters. Pairs occurring as arguments are replaced by their definition before being undefined. If the symbol name in a pair is omitted, the counter is undefined; this deletes both the counter and all its symbols.

verbose

This verb turns on verbose mode. In verbose mode, every pair encountered is printed; this is most useful for debugging input text. By default this mode is off; the command-line option —v will turn it on for all the input. This mode may be turned on with this verb, and turned off with the verb terse.

Note that the control lines are copied to the output, but pairs occurring on them are not replaced. The verbs define, undefine, reset, and print may have more than one argument; but the verbs begin, end, separator, format, prefix, quote, and suffix ignore any text after the first character of the next word. If there is no nonblank word following those verbs, the appropriate character is turned off, so it cannot be matched; since no two control characters may be the same, this is necessary to change one control character to another. For example, if the control character beginning pairs is "<", the control character ending pairs is ">", and they are to be interchanged, the appropriate sequence of commands is:

```
.\" trnum: begin
.\" trnum: end <
.\" trnum: begin >
```

As another example, the following changes the characters which begin and end pairs and separate counter names from symbol names:

After these three lines, {a1,b2} will be recognized as a pair; however, <a1.b2> will not.

V. Use

To run trnum, place it before other preprocessors to NROFF and TROFF; for example,

trnum [-C] [-v] file ... | refer | pic | tbl | eqn | troff

(see [TUTH84], [LESK79], [KERN78], [KERN82], and [OSSA76].) If the file "-"

is encountered, trnum reads from the standard input. If no files are named,

trnum takes its input from the standard input. If the option -v is given, pairs

are printed on the error output as they are encountered in the text. The option

-C puts trnum into a compatibility mode; see the next section.

VI. Compatibility with Older Versions

There are a few visible differences between this version of *trnum* and the earlier version. In earlier versions, the default quote character was '\' rather than '%'; lines with *trnum* verbs began with ".NU"; and several verbs were not recognized. To enable documents written to use this earlier version to be run without

- 11 -

changes, give the -C flag. Note that the new verbs will be recognized, but the

quote character and verb line indicator will be what the earlier version expects.

To determine the version being run, give the command

trnum -I

On the earlier version, this will produce the message

trnum: bad switch -I

and leave trnum waiting for input (just type your end-of-file symbol, usually

control-D, to cause it to exit); on this (and future) versions, it will print a ver-

sion number and date.

VII. A Tutorial

Suppose you are typing a paper, and you decide that you want to number

your tables. Pick a symbol; say, "format". Then, whenever you refer to this

table, rather than saying "table number 1," you would say "table number <for-

mat>". Trnum will replace "<format>" with the appropriate number wherever

it occurs. (If you left off the angle brackets "<...>", trnum would not replace

anything. The angle brackets signal trnum to look at what they enclose; if it is a

legal string (we'll get to what's legal in a bit), then, and only then, does trnum

do the replacement.

Trnum assigns a number to a symbol the first time it is seen; hence, you do

have to be careful in what order you refer to labelled things. For example, in the

input

The next tables give information about the attributes which affect the definitions of counters.

Notice that table <defaults> contains the default

```
settings for the attributes in table <attributes>:
.TS
box, center, tab(;);
c s
cB2 | c
cB2 | 1.
<attributes>. Attributes.
Name; Meaning
prefix; prepended to label
counter; counter name
symbol;symbol name
format; how to print label
suffix; appended to label
.TE
.TS
center, box, tab(;);
C S
cB2 | c
cB2 | c
cB2 | l.
<defaults>. Defaults
What; Default
\ ^{;}Values
prefix;\fInull string\fP
format;\fB1\fP
counter;\fBdefault\fP
suffix;\fInull string\fP
.TE
```

the label "<defaults>" will be replaced by 1, and the label "<attributes>" by 2,

because that is the order the labels occur in the text:

The next tables give information about the attributes which affect the definitions of counters. Notice that table 1 contains the default settings for the attributes in table 2:

2. Attributes.		
Name Meaning		
prefix	prefix prepended to label	
counter	counter counter name	
symbol	symbol symbol name	
format	format how to print label	
suffix appended to label		

1. Defaults	
What	Default
WHAL	Values
prefix	null string
format	1
counter	default
suffix	null string

Unfortunately, it's also backwards - table 1 should precede table 2.

To allow this, trnum lets you define labels on command lines, which begin with ".\" trnum:". Notice that these are ignored by TROFF and NROFF since they are comments. So, to get the labels to come out right in the above example, just before the first line, insert the line

.\" trnum: define <attributes>

Then, since "<attributes>" came before "<defaults>", it will be defined as 1, and the tables will be numbered in the order they appear.

The next tables give information about the attributes which affect the definitions of counters. Notice that table 2 contains the default settings for the attributes in table 1:

1. Attributes.		
Name Meaning		
prefix	prefix prepended to label	
counter	counter counter name	
symbol	mbol symbol name	
format	rmat how to print label	
suffix appended to label		

2. Defaults		
What	Default	
₩ шас	Values	
prefix	null string	
format	1	
counter	default	
suffix null string		

Usually, you want to keep several counts going at the same time; for example, you rarely want to number an equation as 1, the next table as 2, the next

equation as 3, and so forth. What you usually want is to number the first equation as 1, the first table as 1, the next equation as 2, and then refer to them as equation 1, table 1, and so forth. To enable you to do this, trnum has several different counters; each starts at 1. To name a particular counter, prefix the symbol with the counter name followed by a period ".". In the above example, if we wanted to use a counter named "table" to keep track of the tables, we would write "<table.attributes>" and "<table.defaults>" instead of "<attributes>" and "<defaults>", respectively. Like symbols, a counter is initialized when it is first encountered; unlike symbols, when a counter is initialized, it always starts at 1. You can define up to 101 different counters, and if you omit the counter name, a default counter is used. (This counter's name, incidentally, is "default".)

Sometimes you would like to restart a counter at 1. There are two ways to do this. You could delete the counter, and then redefine it with

.\" trnum: undefine < countername.>
.\" trnum: define < countername.>

Alternatively, you could say

.\" trnum: reset < countername.>

which does the same thing. Note the "."; you have to have it or trnum will think you mean the symbol countername and not the counter. Omitting the symbol causes the action to affect the counter rather than a symbol. Also, the string is passed through trnum; unlike strings involving symbols, it is not replaced by anything. Be aware that when you reset or undefine a counter, it undefines all symbols for that counter too.

Incidentally, you can delete a symbol, too. Each counter can have 2039 symbols defined for it; this should be more than enough for most people. However, if it is not, to delete a symbol, say:

.\" trnum: undefine < countername.symbolname>
Resetting a symbol just undefines it, and then redefines it.

Normally, numbers are printed in Arabic format, without any leading zeroes. This is not always what you want; for instance, some people prefer that tables be numbered with Roman numerals. Trnum allows you to control how a counter is printed by a format field. The format field follows the symbol name, and is preceded by a colon (":"). For example, to print the table labels as Roman numerals in the example above, we would write "<table.attributes:I>" and "<table.defaults:I>" (the "I" indicates capital Roman numerals. Other formats available are lower-case Roman numerals (the format indicator is "i"), capital letters (format indicator "A"), lower-case letters (format indicator "a"), and Arabic numerals with or without leading zeroes (indicate this by an Arabic number containing as many digits as you want printed, including leading zeroes.) The format indicator is an attribute of the counter, not of the symbol.

This last comment deserves explanation. When a counter is initialized, several attributes are created (one of which is the format indicator; we'll deal with the others below.) The format specified in the label which creates the counter becomes the default format for that counter. It can be overridden for any label by specifying a format explicitly in that label, but if no format indicator is given, the default one will be used.

```
.\" trnum: define <table.:I>
.\" trnum: define <table.attributes>
The next tables give information about the attributes
which affect the definitions of counters.
Notice that table <table.defaults> contains the default
settings for the attributes in table <table.attributes:00>:
box, center, tab(;);
C S
cB2 | c
cB2 | 1.
<table.attributes>. Attributes.
Name; Meaning
prefix; prepended to label
counter; counter name
symbol;symbol name
format; how to print label
suffix; appended to label
.TE
.TS
center, box, tab(;);
C S
cB2 | c
cB2 | c
cB2 | 1.
<table.defaults>. Defaults
What; Default
\ ^; Values
prefix;\fInull string\fP
format;\fB1\fP
counter;\fBdefault\fP
suffix;\fInull string\fP
```

In this text, all table numbers will be printed as Roman numerals, because when the counter "table" is created (by the first ".\" trnum:"), its format indicator is "I". However, when the number for the label "<table.attributes:00>" is printed, since there is an explicit format indicator with the label (the "00") it will be printed as a two-digit Arabic numeral:

The next tables give information about the attributes which affect the definitions of counters. Notice that table 2 contains the default settings for the attributes in table 01:

1. Attributes.		
Name Meaning		
prefix	prefix prepended to label	
counter	unter counter name	
symbol	ymbol symbol name	
format	how to print label	
suffix appended to label		

2. Defaults		
What	Default	
WHAL	Values	
prefix	null string	
format	1	
counter	default	
suffix null string		

Notice that only the label with the "00" format indicator given explicitly is affected.

There are two other attributes which may be set; a prefix, which is prepended to every label which uses that counter, and a suffix, which is appended to every label which uses that counter, The prefix precedes the counter name and is followed by a plus sign ("+"); the suffix follows the format indicator, and is preceded by a minus sign ("-"). As with the format indicator, the defaults may be explicitly overridden in any label.

Going back to our perennial example, notice in the two lines of text the table number is preceded by the word "table" and a blank. To get this prefix prepended automatically, we would define the counter by:

.\" trnum: define

Then, the sample text becomes:

^{.\&}quot; trnum: define

^{.\&}quot; trnum: define <table.attributes>

The next tables give information about the attributes which affect the definitions of counters.

```
Notice that <table.defaults> contains the default
settings for the attributes in <table.attributes:00>:
box, center, tab(;);
C S
cB2 | c
cB2 | l.
<+table.attributes>. Attributes.
Name; Meaning
prefix; prepended to label
counter; counter name
symbol;symbol name
format; how to print label
suffix; appended to label
.TE
.TS
center, box, tab(;);
C S
cB2 | c
cB2 | c
cB2 | 1.
<+table.defaults>. Defaults
What; Default
;Values
prefix; null string
format;1
counter; default
suffix; null string
.TE
```

(notice the explicitly null prefixes within the tables themselves) and prints as:

The next tables give information about the attributes which affect the definitions of counters. Notice that table II contains the default settings for the attributes in table 01:

I. Attributes.		
Name Meaning		
prefix	prefix prepended to label	
counter	counter counter name	
symbol	symbol symbol name	
format	format how to print label	
suffix appended to label		

II. Defaults		
What	Default	
WHat	Values	
prefix	null string	
format	1	
counter default		
suffix null string		

Suffixes are handled the same way. Note that within the same text, the table numbers in the body of the tables end with a period. However, since a period separates the counter and symbol, it is a control character, and hence must be escaped. Thus, we must write

.\" trnum: define

and the text would look like:

.\" trnum: define

```
.\" trnum: define <table.attributes>
The next tables give information about the attributes
which affect the definitions of counters.
Notice that <table.defaults-> contains the default
settings for the attributes in <table.attributes:00->:
.TS
box, center, tab(;);
C S
cB2 | c
cB2 | 1.
<+table.attributes> Attributes.
Name; Meaning
prefix; prepended to label
counter; counter name
symbol;symbol name
format; how to print label
suffix; appended to label
.TE
.TS
center, box, tab(;);
cB2 c
cB2 c
cB2 | 1.
<+table.defaults> Defaults
What; Default
\^; Values
```

```
prefix;\f2null string\fP
format;\f31\fP
counter;\f3default\fP
suffix;\f2null string\fP
```

As a final example, here is the text of a proof of the irrationality of ϵ , the base of the natural logarithms [RUDI76]:

```
.\" trnum: define <(+equation.:1\-)>
Recall
.EQ <equation.edef>
e^{-}= sum from k=0 to inf {1 over k!} .
.EN
Choose
.EQ <equation.e1>
s sub n = sum from k=0 to n {1 over k!} .
.EN
By <equation.e1> and <equation.edef>, we see
.EQ <equation.e2>
0 < e^{-s} s sub n < \{1 over n!n\}.
.EN
Assume
.I e
is rational;
then $e ~= p over q$,
where
I.
and
Ι.q
are positive integers.
By <equation.e2>,
.EQ <equation.e3>
0 < q! (e^- s sub q) < \{1 over q\}.
.EN
By our assumption, $q!e$ is an integer.
Since by <equation.el>,
.EQ <equation.e4>
q! s sub q "=" q! ( 1 "+" 1 "+" {1 over 2!} "+" ... "+" {1 over q!} )
.EN
is an integer,
we see that $q! (e ~-~ s sub q)$ is an integer.
As q^{-} > = 1,
<equation.e3> implies there is an integer between 0 and 1, contradiction.
```

which produces:

Recall

$$e = \sum_{k=0}^{\infty} \frac{1}{k!} \tag{1}$$

Choose

$$s_n = \sum_{k=0}^n \frac{1}{k!} . \tag{2}$$

By (2) and (1), we see.

$$0 < e - s_n < \frac{1}{n!n}. \tag{3}$$

Assume e is rational; then $e = \frac{p}{q}$, where p and q are positive integers. By (3),

$$0 < q! (e - s_q) < \frac{1}{q}$$
 (4)

By our assumption, q!e is an integer. Since by (2),

$$q!s_q = q!(1+1+\frac{1}{2!}+\cdots+\frac{1}{q!})$$
 (5)

is an integer, we see that $q!(e-s_q)$ is an integer. As $q\geqslant 1$, (4) implies there is an integer between 0 and 1, contradiction.

This covers the basics of *trnum*; the first sections of this guide explain some other, less often used, features. In case you ever want to see what labels you have defined, the line

will cause all defined labels to be printed on the standard error. You can restrict the printing to one counter by naming it, as:

The other forms of this statement are less useful, and are documented in the second section.

The subject of naming things deserves mention. The characters which may be used to name symbols and counters are all letters (both cases), all digits, and underscore ("__"). The characters which may be used in prefixes and suffixes are any except the control characters "<", "+", ".", ":", "-", ">", and "%", and these may be used by prefixing them with the quote character "%". This is fone

specifically to allow string registers to be named in the prefix or suffix strings. So, to print the contents of the string register "*(BF" before the label, and the contents of the string register "*(AF" before the label, you would type:

$$<$$
(BF+countername.symbolname-(AF>

A word of warning when quoting characters: trnum recognizes the quote character only when the next character begins a pair, or when within a pair. In these cases, it throws away the quote character and accepts the next character literally; any special effects which would normally take place, such as beginning another part of the pair, are ignored. Further, if the quote character precedes a character which would normally begin a pair, the quote character is not printed, and no pair is begun. In all other cases, the quote character is simply copied through.

The characters which quote characters, begin and end pairs, and separate parts of a pair, may be reset; but they must not be reset to a character which is one of the control characters. Hence, you could reset the character indicating the beginning of a pair to "{", but not to "+". To get around this, you can "turn off" a control character by defining it to be null, that is,

Acknowledgements

This program grew out of a similar but simpler version written at Purdue University. Subhash Agrawal suggested the idea and helped debug and refine the original program.

References

- [KERN78] Kernighan, Brian W. and Cherry, Lorinda L., "Typesetting Mathematics - User's Guide (Second Edition)," internal memorandum, Bell Laboratories, Murray Hill, NJ 07974 (August 1978).
- [KERN82] Kernighan, Brian W., "PIC A Graphics Language for Typesetting User Manual," internal memorandum, Bell Laboratories, Murray Hill, NJ 07974 (March, 1982).
- [LESK79] Lesk, M. E., "Tbl A Program to Format Tables," internal memorandum, Bell Laboratories, Murray Hill, NJ 07974 (January 1979).
- [OSSA76] Ossanna, Joseph F., "NROFF/TROFF User's Manual," internal memorandum, Bell Laboratories, Murray Hill, NJ 07974 (January 1979).
- [RUDI76] Rudin, Walter, Principles of Mathematical Analysis, Third Edition, McGraw-Hill, Inc., (1976).
- [TUTH84] Tuthill, Bill, "Refer A Bibliography System," UNIX User's Manual, Volume 2, Computer Science Division, Department of Electrical Engineering and Computer Science, University of California, Berkeley, CA 94720 (July 1984).

Appendix - Quick Guide To Trnum

Pairs

<[prefix+][counter.][symbol][:format][-suffix]>

where prefix and suffix are strings to be put before and after (respectively) the text, counter is the name of the counter, symbol is the name of the symbol, and format is the format in which the label is to be printed. Strings for the counter and symbol may contain only alphanumeric and underscore characters; strings for the prefix and suffix may contain any character that is not currently a control character; control characters may be included by quoting them with the quote character. The format string must be one of those in Table I. An Arabic format having n digits specifies a field width of n digits (see the second line of Table I.) Defaults for the attributes are given in Table II. There is no default symbol name.

To force trnum to ignore a pair, precede it with the quote character, or set the prefix character to ASCII NUL, or put the line ".\" trnum: off" before the pair, and the line ".\" trnum: on" after it.

Changing Control Characters

These are listed in Table III and are given as the first word after the colon on lines beginning with ".\" trnum:". The control character is changed to the first character of the second word, or set to ASCII NUL if there is no second word; the rest of the line is treated as though there were no verb there.

Other verbs

These are listed in Table IV and are given as the first word after the colon on lines beginning with ".\" trnum:".

Use

$$trnum \left[\begin{array}{c} -C \end{array} \right] \left[\begin{array}{c} -I \end{array} \right] \left[\begin{array}{c} -v \end{array} \right] \textit{file} \ldots \left| \begin{array}{c} refer \end{array} \right| \ tbl \left| \begin{array}{c} eqn \end{array} \right| \ troff$$

If the file "-" is encountered, trnum reads from the standard input. If no files are named, trnum takes its input from the standard input. If the option -v is given, pairs are printed on the error output as they are encountered in the text. If the option -I is given, the version number and date are printed and trnum exits. If the option -C is given, trnum will correctly process files intended for the first version.

Tables

Table I. Formats		
Format Numbering Sequence		
1	1,2,3,4,5,	
001	001,002,003,004,005,	
i	i,ii,iii,iv,v,	
1	I,II,III,IV,V,	
	a,b,c,,z,aa,ab,,zz,aaa,	
A	A,B,C,,Z,AA,AB,,ZZ,AAA,	

what	initial value	verb to
begin format	:	format
end counter		separator
begin pair	<	begin
end pair	>	end
begin suffix	-	suffix
end prefix	+	prefix
quote	ĺ۱	quote

Table II. Default		
What	Default Values	
prefix	null string	
format	1	
counter	default	
suffix	null string	

Table IV. Miscellaneous Verbs	
what	effect
control	print control characters on stderr
define	define counter or symbol
off	turn trnum off
o n	turn trnum on
print	print defined pairs on stderr
reset	undefine, then define counter or symbol
terse	turn off -v option
undefine	delete counter or symbol
verbose	turn on -v option